

## How to Develop Film

(All steps at temperature as much as possible– 68° F /20° C)  
8 fluid ounces per roll of film

IN TOTAL DARKNESS

1. Prewet (water at temperature) 1 minute  
rap the tank on its corner on a hard surface (the floor works well in our film developing room)

2. Developer D-76 1+1 (1:1) 11 minutes  
Start pouring in as the clock starts. Once tank is full, agitate for the first 30 seconds. After that, agitate for 10 seconds per minute. Start pouring out 30 seconds before the time is up.

3. Stopbath (water rinse, fill and empty tank, about 30 seconds)

4. Fixer – Kodak Rapid Fix, 3-10 minutes. (Twice the time it takes to clear a piece of film.)

Agitate as with developer.

**Pour into Fixer recovery tank, never down the drain!**

5. Water rinse, 30 seconds.

6. Fixer Remover 4 minutes (agitate 10 seconds per minute)

7. Water wash 8-10 minutes

8. PhotoFlo, bathe film about 30 seconds

Hang it up to dry in the drying cabinet and close the door. Turn the heat on medium if you must.